DEPARTMENT OF PRIMARY INDUSTRIES

Agriculture Notes



Note Number: AG1245 Published:July 2006 Updated: August 2008

Forage Cereals: Harvest and Storage:-Storage of Whole-Crop Cereal Silage

Although the preferred method for harvesting forage cereals is by precision chopping into bulk storage, many farmers will use balers.

This Agnote deals mainly with storage options for both methods of harvesting and the critical management necessary for efficient storage of forage cereals.

Introduction

Precision chopping is the preferred method for harvesting whole-crop cereal silage compared to baling, despite the latest balers having chopping mechanisms as an option. The very short chop length achieved by a precision chopper facilitates the compaction of the stored product, particularly when made at the later growth stage, soft dough.

Forage cereals may be baled at the vegetative stage but the crop must be mown and wilted to over 33% DM to ensure a satisfactory (lactic acid) fermentation. Bales must be densely compacted and this is more effective using balers with chopping mechanisms.

Baling forage cereals at the soft dough stage, even using balers with chopping mechanisms, although not impossible, often does not achieve a high enough density in the bales. Apart from increased amounts of air trapped in the bales leading to dry matter and nutritive losses, plus possible puncturing of the plastic seal by the stalks, they are prone to damage by vermin due to the presence of grain. See Agriculture note AG1244 Forage Cereals: Harvest and storage:- Harvesting whole-crop cereal silage.

The material stored in any storage system must be compacted as densely as possible in its storage package, sealed airtight as soon as possible after harvesting is completed, and be regularly inspected for holes and repairing damage with specific silage plastic film tape as soon as possible.

Whole-crop cereal silage storage systems:

Forage harvested as bulk storage

Stacks above ground



- Concrete bunkers
- Pits in the ground
- Stretchable bags

Baled silage storage

- Individually wrapped bales
- Continuously wrapped in-line "sausage"
- Stretchable tubes or "socks"
- Above ground storage under plastic sheets
- Pits below ground.

Forage harvested as bulk storage

Precision chopped material can be stored in stacks or walled bunkers above ground or in pits in hillsides, along bank walls, etc. They can also be stored in stretchable sausage bags.

Pits/stacks/bunkers

Precision chopped forage, being very short in length but ideal for compaction, will not bind in a stack compared to longer material. In particular, material harvested at the soft dough stage may tend to "move" when rolled by the compacting machinery. To minimise this and the danger it may present to operators, stacks with some type of side constraint, such as in ground pit, dirt walls or cement walled bunkers, are preferable to rectangular or circular bun stacks above ground.

Compacting the stack

The stack should be continuously rolled with a very heavy and preferably a wheeled tractor. However some contractors are now using dual wheeled tractors or very heavy excavators (tracks) for safety reasons.

Spread the material in layers of about 15 cm to allow for improved compaction (air exclusion) compared to thicker layers. Rolling slowly rather than quickly is essential to allow the weight of the rolling machine to exert downward pressure Aim for a packing density of about 250 kg DM per cubic metre although this may be lower with longer chopped and/or drier material. Density is influenced by DM content, chop length, stack depth, weight of compacting machine and period of compaction. A general rule of thumb for ensuring maximum compaction based on the weight of the packing or rolling tractor is:

Weight of packing tractor (kg) \div 300 = Delivery rate (tonnes of fresh crop per hour).

Eg. 18 000 kg tractor \div 300 = 60 tonnes/hour.

A stack being filled over several days should be covered overnight with a plastic sheet to minimise plant respiration and heating. Each new day's harvested material should, ideally, cover yesterday's material by a depth of at least one metre to prevent continued respiration of the earlier harvested material.

If on the second or third day of filling a stack, a hand pushed into the face up to the wrist feels very warm or hot, then aerobic deterioration is occurring at a rapid rate, ie. lost DM and nutritive value plus rapid increases of yeast and moulds. This could be caused by inadequate compaction due to the material being cut too long, too dry, the rolling machine is too light or rolling speed may be too fast.

Keep silage free of contaminants. Mud, dead animal carcasses, decaying plants, etc. must not enter the storage as the bacteria they contain will be deleterious to the fermentation process. Ensiled carcasses can cause animal deaths due to botulism.

Sealing the stack

Once harvesting and the final compaction is completed, seal the storage airtight, using plastic sheets specifically manufactured for silage (>150 micron thickness). Most commonly used is the co-extruded white-black plastic, placing the white side up to reflect the sun's heat.

Then place weighting over the entire surface area of the stack. Car tyres, all touching each other, are commonly used (See Figure 1). Be wary of holing the plastic from wire in tyres, your foot imprints, etc.



Figure 1. Stack well weighted, well sealed and airtight

If several sheets are used for sealing, overlap the plastic by at least one metre, placing tyres along the overlap. The edges should, ideally, be buried under soil, with the dirt covering the edges. If placing tyres along the plastic edge, have at least two rows width, and preferably the soil graded smooth underneath to allow a better seal.

"Sausage" bags made from last year's plastic (See figure 2) is an alternative to tyres. These are very useful on the plastic overlaps, for sealing the stack edges on the ground or along the insides of bunker walls. They follow the indentations of the ground or stack surface being slightly flexible in structure. Where two rows of are used, overlap the "sausage" bags rather than laying them together side by side, to minimise air entering where the ends meet.



Figure 2. Plastic "sausage" bags

Stretchable Bags

These are large stretchable bags or tubes into which forage, mainly used for maize silage, is compressed to a certain level of pressure. The bag stretches to a set tolerance and the tendency to contract maintains an airtight storage. Whole-crop material must be chopped very short and well compressed to ensure satisfactory storage conditions with these bags. The storage (plastic bag) should last at least 2 - 3years before the plastic loses its integrity, allowing air to enter.

Baled silage storage

Round and square baled whole-crop cereal silage must be compacted densely and sealed airtight within one to two hours after baling. Round bales, preferably should be chopped to aid compaction, fermentation and allows an increase in animal intakes given the extremely long cereal plants. Chopping is particularly important when baling at the later soft dough stage when stems are more lignified and hollow. However square bales are very dense in nature after baling and chopping is optional although desirable for increased intakes

Individually wrapped bales

and use in TMR mixer wagons.

Individually wrapped bales must be sealed over their entire surface area with at least four layers of stretchwrap plastic with 50% overlap, using 55% stretch. However there are some products available which have undergone some "prestretching" at the manufacturing facility and may require modifications to the pre-stretcher gearing.

Be aware that most countries overseas, including New Zealand, advocate a 70% stretch thereby stretching the plastic thinner, so requiring 6 layers of plastic.

However, applying six layers in Australia provides added insurance against air intrusion into the bale, and especially so if it is being deposited onto stubble. The extra layers also give a strengthened seal if bales are being transported after



wrapping. Six layers are essential if the baled crops are stemmy and/or stalks are inclined to protrude.

The extra layers will most likely allow two years storage time instead of the manufacturers' guaranteed 12 months using 4 layers.

Bales should be stored on their ends to maintain their shape and to present the multi-layered ends to the sunlight and birds and problematic insects and grubs at ground level.

Continuously wrapped in-line "sausage"

Continuously wrapped bales also use the stretchwrap plastic stretched to 55% but is overlapped by 75% (See Figure 3). This system will reduce the amount of stretchwrap film used per bale by about 30 - 40%. The bales should be of even diameter to prevent over stretching of the film where the bales meet. If the line of bales is long, segment the run in several places by inserting a seal, eg. wrapped bale, to act as a "plug" if feeding out is stopped before the line is completely fed out.



Figure 3. Continuous in-line sausage

Bird problems in this system may be reduced by stretching hay netwrap along the length of the rows of bales (See Figure 4).



Figure 4. Netwrap placed on bales to reduce bird problem

Stretchable "sausage" tubes

These are large diameter plastic bags or "socks" which contract onto the bale once inserted (See Figure 5). Although an uncommon and relatively expensive method for storing bales the film is strong and offers a storage possibility for 2 –



A machine is required to expand the diameter of the plastic to allow insertion of the bales and the film then contracts tightly back onto the bale. Bale diameters should be even so that air is not trapped in the space left between large and small diameter bales. Mould and yeast grow in these areas resulting in losses and reduced palatability.



Figure 5. Plastic tubeline storage system

Bird and vermin control

Birds and vermin can be a serious problem with baled silage made at the soft dough stage. Removing the bales from the paddock, if possible, within hours of harvest may diminish the problem with birds. Stringing plastic humming wires (used by orchardists for detracting birds) may also help or but netting placed on tyres over the bales is a positive control technique. Vermin, field mice in particular, appear to "sense" the grain of whole-crop forage baled at the grain formation stage. They will chew many holes through the plastic resulting in large losses. To minimise this, store the bales on a cleared (preferably sanded) area, leaving the bales spaced to allow regular inspection and immediate repair. The use of suitable baits, placed a small distance from the storage site, will assist. A "hilled" circle of slaked lime around the circumference of the bales is often useful as the mice dislike the effect of the lime on their claws, and unsafe nature of the hill.

Above ground storage under plastic sheets

Round bales

Storing unwrapped round bales under sheets of plastic above ground is not recommended for whole-crop cereal silage due to the inherent air pockets unavoidably formed in these systems. Whole-crop cereal silage is very prone to aerobic deterioration and spoilage. Unwrapped round bales under sheets of plastic will invariably result in substantial losses (DM and quality), not to mention the disasters likely to occur due to poor sealing or puncturing of the sheet.

Large square bales

Due to their shape and density, large square bales can be reasonably satisfactorily stored above ground under sheets of plastic. However seal must be airtight at the base and maintained "hole free". Due to the unavoidable variation in bale lengths, stack the bales along one side and adjoining side



to form straight edges. The remaining two edges will be uneven and trap air once sealed. Store only enough bales for 14 - 16 days feed in each compartment in this system.

Pits below ground

Round bales

Storing unwrapped round bales of WCS in pits is not recommended for the same reasons given for not storing above ground under sheets.

Large square bales:

Large square bales are much more suited to storing in pits if stacked tightly and the edge seals are airtight. If designing a pit for large square bales, and the soil type allows, aim for vertical sides to assist with stacking, air reduction, and sealing. Stack the bales tightly against one side of the pit and the back to minimise air entrapment. This will leave one side with uneven edges, and possibility of trapping air. If possible, lay the plastic down into the pit on the side with the uneven bale ends. Then place some sand or soil down between the plastic and wall to force out air.

If the soil type necessitates the pit sides to be battered, ie. sloped, storing and sealing will be more difficult and expensive to achieve.

Placing a thin layer of soil or sand on the plastic sheet on top of the stack will minimise air travelling back along the top and

ISSN 1329-8062

Published and Authorised by:

Department of Primary Industries 1 Spring Street Melbourne, Victoria

This publication is copyright. No part may be reproduced by any process except in accordance with the provisions of the Copyright Act 1968.

This document was provided as a PDF document from the DPI website

For more information about DPI visit the website at www.dpi.vic.gov.au or call the Customer Service Centre on 136 186

The advice provided in this publication is intended as a source of information only. Always read the label before using any of the products mentioned. The State of Victoria and its employees do not guarantee that the publication is without flaw of any kind or is wholly appropriate for your particular purposes and therefore disclaims all liability for any error, loss or other consequence which may arise from you relying on any information in this publication



side of the stack thereby preventing spoilage. Tyres touching each other on top will suffice but will not be as effective. Use sheets of plastic to compartmentalise the stack into individual and independent modules of about 14 - 21 days feed per section.

Acknowledgments

I acknowledge contribution by Joe Jacobs of DPI, Victoria, and Julian Hill, University of Melbourne.

We acknowledge the contribution to this Agnote by Project 3030, which is jointly funded by Dairy Australia, the Victorian Department of Primary Industries and the University of Melbourne.



This Agnote was developed by Frank Mickan, Ellinbank. July 2006.